

CONFIDEA G4

RELEASE NOTES



COPYRIGHT STATEMENT

No part of this publication or documentation accompanying this product may be reproduced in any form or by any means or used to make any derivative such as translation, transformation, or adaptation without the prior written permission of the publisher, except in case of brief quotations embodied in critical articles or reviews. Contents are subject to change without prior notice.

Copyright © **2021** by Televic Conference NV. All rights reserved.

The authors of this document have made every effort in the preparation of this book to ensure the accuracy of the information. However, the information in this manual is supplied without warranty, either express or implied. Neither the authors, Televic Conference NV, nor its dealers or distributors will be held liable for any damages caused or alleged to be caused either directly or indirectly by this book.

TRADEMARKS

All terms mentioned in this manual that are known to be trademarks or service marks have been appropriately capitalized. Televic NV cannot attest to the accuracy of this information. Use of a term in this book should not be regarded as affecting the validity of any trademark or service mark.

DOCUMENT HISTORY

| Version | Date | Description |
|---------|------------|------------------------------|
| 0.1 | 2021-07-06 | Release notes version 1.2.10 |
| 0.2 | 2021-09-10 | Release notes version 1.2.11 |

CONTENTS

| | |
|--------------------------------------|---|
| Document history..... | 3 |
| IMPORTANT COMPATIBILITY NOTICE | 4 |
| CONFIDEA G4 1.2.X..... | 5 |

IMPORTANT COMPATIBILITY NOTICE



Confidea G4 is not compatible with CoCon software.

CONFIDEA G4 1.2.X

WHAT'S NEW

- Support for IEEE 802.1x authentication
Link to manual section: [Settings \(tcs-static.azurewebsites.net\)](https://tcs-static.azurewebsites.net/Settings)
- Support for Confero PLAN and MEET
- Support for secure customer API

- Next-in-line button available for use when no meeting started in Confero
- Voting labels now show text labels for 4 character iso symbols +,0,-
- Added the following countries to WAP region AROW
 - Azerbeidjan
 - Iran
 - Jordan
 - Israel
- Animation shown on FLEX units while update is in progress
- Show the FLEX units IP address in the settings menu of the unit

FIXED ISSUES

- Network configuration settings are not part of the export / import capabilities anymore
Note : downgrading to a version <1.2 will result in reset of the network settings to default values
- Fixed a wrong link to section of manual
- Added a 24h margin in the license validity check.
- Removed country indication for regions North America and Japan as not relevant.
- Fixed various issues with charger:
 - In some occasions charging process not started when inserting battery in charging slot (TCS_G4-1480)
 - In some occasions battery inserting was not detected (TCS_G4-1479)
 - Sporadic errors reported on battery slot (TCS_G4-1450)
- Wrong routing of floor to Dante (TCS_G4-1488)

KNOWN ISSUE

- Not possible to update Confidea FLEX units with version 1.1.x or lower when the WAP runs a version 1.2.x or higher. Downgrade the WAP to version 1.1.x in order to update the complete system to a higher version.

Warning added when there is an incompatibility detected with explanation on what to do to upgrade total solution.

- Refresh of web-browser needed on order to see the correct status of licenses after a configuration is imported (TCS_G4-1579)
- Very rarely observed: No upstream audio after seat re-ordering. Everything is fine after reboot (TCS_G4-1546)
- Camera protocol interface value not always visualized correctly, correct after refresh. (TCS_G4-1471)

MANUAL

<https://tcs-static.azurewebsites.net/ConferoManual>

